PAINTING GUIDE

TUDOR WALLS, FAÇADES AND FLOORS



BEFORE YOU BEGIN

This paint guide is an update to our previous City Builder System paint guide for Tudor themed pieces to closer match the most recent paint masters of our factory-finished pieces. The Tudor Floor is being phased out for our newer Rustic Wood Floors, but the paint steps have been included in this guide. You can still reference our original City Builder System paint guide at dwarvenforge.com/blogs/paint-guides/city-builder-system-tudor-buildings

TUDOR WALLS

STEP 1



BLACK
(GT002-B)

Paint all wooden components on your walls and roofs with a **Black** base coat.

STEP 2



BASE WOOD
(GT002-BW)

Apply a heavy dry brush layer of **Base Wood** over the wooden components.

STEP 3



BASE WOOD
(GT002-BW)

+

STUCCO
(GT002-ST)

Mix **Base Wood** and **Stucco** in a 1:1 ratio. Using this mixture,lightly dry brush over the wooden components of each piece.

STEP 4



STUCCO
(GT002-ST)

+

LAVA YELLOW
(GT002-LY)

+

WHITE
(GT002-W)

Mix **Stucco**, **Lava Yellow**, and **White** in a ratio of 2:2:1. Apply this mix in layers on the Tudor stucco sections until the yellow paint is fully opaque. This should take 2-3 coats.

STEP 5



EARTH STONE
(GT002-ES)

For pieces like the center window wall with weathered stucco, apply **Earth Stone** to the “damaged” areas of the stucco below the window using a #1 (Details) brush.

STEP 6



BASE WOOD (GT002-BW)

+

EARTH STONE (GT002-ES)

+

BLACK (GT002-B)

Mix **Base Wood**, **Earth Stone**, and **Black** in a 2:2:1 ratio with some water. Apply this wash over the tudor stucco areas. Concentrate the wash on the edges of the yellow stucco the most.

DOOR WALLS

STEPS 1 - 4

Step 1: Follow the Tudor Walls steps above for the wood wall and stucco portion of this piece.



BASE WOOD (GT002-BW)

Step 2: Lightly dry brush **Base Wood** over the door texture. Let this dry before moving on to next step.

STUCCO (GT002-ST) + EARTH STONE (GT002-ES) + BASE WOOD (GT002-BW)

Step 3: With an even lighter feather touch than before dry brush a mixture of **Stucco**, **Earth Stone** and **Base Wood** in a 2:2:1 ratio.

optional

BLACK (GT002-B)

SYSUUL SILVER (GT002-SYSS)

Step 4: Paint all metal details on door with **Sysuul Silver**. (Optional) You can base coat the details first with **Black** so that the metallic will really pop.

ORIEL WINDOW FAÇADE
STEPS 1 - 3



Step 1: Follow the Tudor Walls steps above for the wood and stucco portions of this piece.

STONE EDGE DRY BRUSH (GT002-SE)

Step 2: Use **Stone Edge Dry Brush** to full in the braided details above and below the windows. Also create an outline by filling in the creases of the braids.

CARDBOARD (GT002-CB)

Step 3: With an opaque layer of **Cardboard**, paint the interior (inside the crease) of the braid detail.

ORIEL WINDOW ROOF
STEPS 1 - 3

DEEP WATER GREEN (GT002-WG) + BLACK (GT002-B)

Step 1: Paint entire piece a mix of **Deep Water Green** and **Black** in a 2:1 ratio.



BASALT BLUE (GT002-BASB) + WHITE (GT002-W) + CARD-BOARD (GT002-CB)

Step 2: Avoiding the metal molding, use a mix of **Basalt Blue**, **White**, and **Cardboard** in a 4:2:1 ratio, opaquely paint the bottom edges of the roof and blend upwards using the dry brush method so that the base green color is still visible near the metal molding trim.

CARDBOARD (GT002-CB)

Step 3: Paint in the metal molding trim in **Cardboard**.

BRAIDED COTTAGE MOLDING
STEPS 1 - 4

Step 1: Follow the Tudor Walls steps above for the wood portions of this piece.

DEEP WATER GREEN (GT002-WG) + BLACK (GT002-B)

Step 2: Paint the inset of the sculpt with a mixture of **Deep Water Green** and **Black** in a 2:1 ratio.



BASALT BLUE (GT002-BASB) + WHITE (GT002-W) + CARD-BOARD (GT002-CB)

Step 3: Dry brush the inset with a 4:2:1 ratio of **Basalt Blue**, **White**, and **Cardboard**. Try to avoid the outer rim.

CARDBOARD (GT002-CB)

Step 4: Opaquely paint in the knot detail with **Cardboard**.

TUDOR WOOD FLOOR

STEPS 1



BASE WOOD
(GT002-BW)

Apply **Base Wood** over the entire surface and edges of the piece with a #3 (Painting) brush. Be careful not to apply too much paint. Use a light hand (avoid painting into the deeper areas) to bring out the texture. Let the paint dry before moving to the next step.

STEPS 2



STUCCO
(GT002-ST)

+

EARTH STONE
(GT002-ES)

+

BASE WOOD
(GT002-BW)

Dab a very small amount of a mixture of **Stucco**, **Earth Stone** and **Basewood** in a 2:2:1 ratio onto a #12 (Drybrush) brush, then dab the brush onto a paper towel to remove excess paint.

With a feather light touch, apply over the surface of the wood, to create highlights. Let the paint dry before moving to the next step.

STEPS 3



optional

BLACK
(GT002-B)

SYSUUL SILVER
(GT002-SYSS)

Paint all metal nails on floor with **Sysuul Silver**. (Optional) You can base coat the nails first with **Black** so that the metallic will really pop.